

# Changing, adding and disabling L1 cache

2025

StarWind Documents















#### **Trademarks**

"StarWind", "StarWind Software" and the StarWind and the StarWind Software logos are registered trademarks of StarWind Software. "StarWind LSFS" is a trademark of StarWind Software which may be registered in some jurisdictions. All other trademarks are owned by their respective owners.

#### **Changes**

The material in this document is for information only and is subject to change without notice. While reasonable efforts have been made in the preparation of this document to assure its accuracy, StarWind Software assumes no liability resulting from errors or omissions in this document, or from the use of the information contained herein. StarWind Software reserves the right to make changes in the product design without reservation and without notification to its users.

#### **Technical Support and Services**

If you have questions about installing or using this software, check this and other documents first - you will find answers to most of your questions on the <u>Technical Papers</u> webpage or in <u>StarWind Forum</u>. If you need further assistance, please <u>contact us</u>.

#### **About StarWind**

StarWind is a pioneer in virtualization and a company that participated in the development of this technology from its earliest days. Now the company is among the leading vendors of software and hardware hyper-converged solutions. The company's core product is the years-proven StarWind Virtual SAN, which allows SMB and ROBO to benefit from cost-efficient hyperconverged IT infrastructure. Having earned a reputation of reliability, StarWind created a hardware product line and is actively tapping into hyperconverged and storage appliances market. In 2016, Gartner named StarWind "Cool Vendor for Compute Platforms" following the success and popularity of StarWind HyperConverged Appliance. StarWind partners with world-known companies: Microsoft, VMware, Veeam, Intel, Dell, Mellanox, Citrix, Western Digital, etc.

#### **Copyright ©2009-2018 StarWind Software Inc.**

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording or otherwise, without the prior written consent of StarWind Software.




More information about L1 cache is available on the link

: https://knowledgebase.starwindsoftware.com/explanation/starwind-virtual-san-l1-and-l2 -caches-operational-principles/


**Note:** It is not recommended to configure cache in Write-Back mode on Standalone devices in order to avoid possible data corruption upon power outage or incorrect service shutdown.

## **Disabling Cache**

1. Stop the StarWind service.



the folder containing the \*.swdsk StarWind device header file(s):




3. These are the lines to be removed from \*.swdsk device header file(s):

```
<caching>
  <cache type="write-back" size="128" units="MB" level="1">
        <storages>
        <storage_ref id="1"/>
```



**NOTE:** Units and size values may differ from the ones provided in the above example. 4. Save the file(s). 5. Start the StarWind service.




synchronization to complete, then repeat the same steps on the other node(s).


## **Changing Cache Size And Type**

1. Stop the StarWind service.





the folder containing the \*.swdsk header file(s):



3. These are the lines to be edited from \*.swdsk header file(s):


```
<caching>
                       <cache type="write-back" size="128" units="MB" level="1">
                            <storages>
                                 <storage ref id="1"/>
                            </storages>
                       </cache>
                 </caching>
and
                 <storage id="1" name="RAM" type="RAM">
                       <interval size="128" units="MB"/>
                 </storage>
where:
Parameter
                               Storage method in which data is written into the cache and the corresponding main memory location at the same time. The cached data allows for fast retrieval on demand, while the same data in main memory ensures that nothing gets lost if a crash, power failure, or other system disruption occurs.
                   write-back
                               During idle machine cycles, the data are written from the cache into memory or onto disk. Write back caches improve performance, because writing to the high-speed cache is faster than to normal RAM or disk. Using write-back cache for disks adds a slight amount of risk, because the data remain in volatile memory longer.
```



size (value) Cache size in the corresponding units "MB", "GB".

storage\_ref id storage
(value) {value} "Storage\_id" and "storage\_ref id" should be the same for device type, but differ from 1, because the main device storage has this reference index. You can set this number to 3 or 4, for example.


**NOTE:** Units and size values may differ from the ones provided in the above example. 4. Save the file(s). 5. Start the StarWind service.



synchronization to complete, then repeat the same steps on the other node(s).


## **Adding Cache**

1. Stop the StarWind service.



the folder containing the \*.swdsk header file(s):





**NOTE:** "Storage id" and "storage\_ref id" should be the same for device type, but differ from 1, because the main device storage has this reference index. You can set this number to 3 or 4. These are the lines to be added to both .swdsk HA and image header files of the device:

• After the closing </geometry> tag:

• After the *<storages>* tag which is below the *<resources>* tag:

```
<resources>
<storages>
<storage id="4" name="RAM" type="RAM">
<interval size="128" units="MB"/>
</storage>
```

#### where:

 Parameter
 Value
 Description


 cache type
 write-through
 Storage method in which data is written to thing gets lost if a crash, power failure, or other system disruption occurs.

 unite-back
 buring idle machine cycles, the data are written from the cache into memory or onto disk. Write back caches improve performance, because writing to the high-speed cache is faster than to normal RAM or disk. Using write-back cache for disks adds a slight amount of risk, because the data remain in volatile memory longer.

 storage\_ref id storage
 Value} { value}

**NOTE:** Units and size values may differ from the ones provided in the above example. 3. Save the file(s). 4. Start the StarWind service.






synchronization to complete, then repeat the same steps on the other node(s).

## Instructions For Devices Originally Created In Starwind Vsan 6.\*


## **Disabling Cache**

1.Stop the StarWind service



folder where the StarWind.cfg file is located:






3. Search for entries for HA devices in StarWind.cfg like the one below :

```
<device name="ImageFile1" file="My Computer\C\h.img" asyncmode="yes"
CacheMode="wt" CacheSizeMB="512"/>
```

4. Change CacheMode="wt" to CacheMode="none":

5. Save the StarWind.cfg file. 6. Start the StarWind service.




synchronization to complete, then repeat the same on the other node **NOTE**: Device name and other parameters may differ from the ones in the above example.


## **Changing Cache Size**

1. Stop the StarWind service.





folder where the StarWind.cfg file is located:




3. Search for entries for HA devices in StarWind.cfg like the one below:

```
<device name="ImageFile1" file="My Computer\C\h.img" asyncmode="yes"
CacheMode="wt" CacheSizeMB="512"/>
```

4. Change CacheSizeMB="512" to CacheSizeMB="{value}" where {value} is the required L1 cache size: 5. Start the StarWind service.





synchronization to complete, then repeat the same on the other node **NOTE:** Device name and other parameters may differ from the ones in the above example.

## **Request A Product Feature**

To request a new product feature or to provide feedback on a StarWind product, please email to our support at <a href="mailto:support@starwind.com">support@starwind.com</a> and put "Request a Product Feature" as the subject.



#### **Contacts**

US Headquarters	EMEA and APAC
+1 617 829 44 95	+44 2037 691 857 (United Kingdom)
+1 617 507 58 45	+49 800 100 68 26 (Germany)
+1 866 790 26 46	+34 629 03 07 17 (Spain and Portugal)
	+33 788 60 30 06 (France)

Customer Support Portal: <a href="https://www.starwind.com/support">https://www.starwind.com/support</a>

Support Forum: <a href="https://www.starwind.com/forums">https://www.starwind.com/forums</a>

Sales: <a href="mailto:sales@starwind.com">sales@starwind.com</a>

General Information: <a href="mailto:info@starwind.com">info@starwind.com</a>



**StarWind Software, Inc.** 100 Cummings Center Suite 224-C Beverly MA 01915, USA <a href="https://www.starwind.com">www.starwind.com</a> © 2025, StarWind Software Inc. All rights reserved.